

Pleural Effusion and Empyema

A plain-English guide for you and your family

WHAT IS HAPPENING

Wrapped around each lung is a thin, slippery two-layer sack called the pleura — picture a balloon inside a bigger balloon with just a tiny film of fluid between them so they can slide past each other when you breathe. Normally that space holds only a tablespoon of fluid; the body makes a little and the lymph vessels under the ribs soak it back up at the same speed, keeping the amount steady. When something breaks that balance — when pressure in the blood vessels pushes extra fluid out (like in heart failure), when protein in your blood drops so fluid leaks (like in liver failure or kidney disease), when vessel walls get leaky from inflammation (like in pneumonia, cancer, or a blood clot in the lung), or when the lymph drains get blocked — fluid piles up in that thin space. The kind of fluid that forms depends on the cause: watery and low-protein (called a transudate) if it is a pressure or protein problem, or thick and high-protein (called an leaked fluid (exudate)) if it is inflammation, infection, or cancer. Either way, the growing pool of fluid squeezes the lung from the outside, so less air gets in and you feel short of breath. If bacteria get into that fluid and start growing, white blood cells rush in to fight, the fluid turns to pus, the pH drops below 7.2, and you have an empyema — infected fluid that must be drained with a chest tube or it will scar the lung into a thick rind. None of this is random. Every weird finding — the dull thump when the doctor taps your chest, the quiet breath sounds, the shortness of breath — traces back to one thing: fluid is taking up space where air should be, and your lung is trapped.

What you might feel

- Shortness of breath that gets worse when lying flat
- Sharp chest pain that gets worse when you breathe in or cough
- Dull sound when you tap on the chest over the fluid
- Quiet or absent breath sounds at the bottom of the lung
- Less chest vibration when you place your hand on the chest while the patient talks
- A rubbing or grating sound when you listen to the chest, especially early on
- The trachea (windpipe) shifts away from the side with fluid if there is a fluid collection (effusion) is very large

- Fever and sweats, especially if the fluid is infected (empyema)

Call the doctor right away if...

- Trachea (windpipe) shifted away from the side with fluid — means very large a fluid collection (effusion) or tension, need urgent drainage
- Fever, foul-smelling fluid, or pus on aspiration — means empyema (infected fluid), needs chest tube and antibiotics right away
- Re-expansion pulmonary edema (fluid flooding the lungs) after draining more than 1-1.5 liters too fast — lung fills with watery fluid and oxygen drops; drain slowly and stop if cough or chest tightness starts
- Fluid keeps coming back after drainage — may mean cancer, tuberculosis, or heart failure is not controlled; needs full work-up

What the care team will do

- Check oxygen saturation every 1 to 2 hours and give oxygen to keep SpO2 above 90 percent
- Position the patient sitting upright at 45 to 90 degrees or leaning forward on a bedside table
- Monitor respiratory rate, work of breathing, and use of accessory muscles (neck and shoulder muscles) every 2 to 4 hours
- Measure and record the amount, color, and clarity of fluid drained during thoracentesis or from the chest tube every shift
- Watch for sudden cough, chest tightness, or dropping oxygen saturation during or right after drainage
- Assess pain level every 4 hours and give ordered analgesics before procedures or chest tube repositioning
- Check chest tube for kinks, clots, or disconnection every 2 hours and keep the drainage system below the chest at all times
- Monitor temperature every 4 hours and report fever above 100.4 degrees Fahrenheit or new chills

Medicines you may be given — and why

Furosemide (Lasix)

Furosemide makes the kidneys dump extra salt and water into the urine. When the body has too much fluid—like in heart failure—this pill helps pull that extra water out of the blood

vessels and tissues, including fluid that leaked around the lungs. It does NOT treat the infection or inflammation itself; it only drains the extra fluid load when the heart cannot pump well enough to keep fluid where it belongs.

Antibiotics (choice depends on the germ)

Antibiotics kill or stop the bacteria that invaded the pleural space and turned clear fluid into pus (empyema). Different antibiotics attack bacteria in different ways—some blow holes in the bacterial wall, some jam the germ's protein factory, some wreck its DNA copier. The goal is to pick drugs that cover the most likely bugs (often mouth bacteria that snuck in after pneumonia, or skin bacteria from surgery or trauma) and adjust once culture results name the exact germ.

Tissue plasminogen activator (tPA) PLUS DNase (dornase alfa)

When empyema becomes thick and loculated (trapped in pockets by fibrin strands and sticky DNA from dead white cells), a chest tube alone cannot drain it. tPA breaks down the fibrin glue, and DNase chops up the DNA nets. Together they turn thick pus into thinner liquid that a tube can suck out, avoiding surgery in many cases. This combo is squirted directly into the pleural space through the chest tube, NOT into the bloodstream.

Talc pleurodesis (sterile talc powder)

For effusions that keep refilling—especially from cancer that cannot be cured—talc pleurodesis glues the lung to the chest wall so fluid cannot pool between them anymore. Sterile talc powder is puffed into the pleural space (usually during a VATS procedure or through a chest tube). The talc triggers intense inflammation; as the inflammation heals, the two pleural layers scar together (symphysis). No gap means no room for fluid to collect.

Indwelling tunneled pleural catheter (e.g. PleurX)

A soft flexible tube is placed under the skin and into the pleural space, with a one-way valve on the outside end. The patient (or a nurse) drains fluid at home every 1–3 days by connecting a vacuum bottle to the valve. This avoids repeated hospital taps and lets people stay comfortable at home, especially when the cancer cannot be cured and pleurodesis has failed or the lung is trapped. Over time, some catheters auto-pleurodesise (the space scars shut on its own in about 40–50 % of patients), and the catheter can be removed.

Where this information comes from

- British Thoracic Society Pleural Disease Guideline 2023
- American Thoracic Society guidelines on pleural effusion
- IDSA guidelines on empyema and complicated parapneumonic effusion

- NEJM review of pleural effusion evaluation and management

Last reviewed: 2026-07-07